




Smartape Software Installation Guide



Software has to install at Windows 11 (New PC is advised)

1 Presetting


(1) Disk Partition



Do not install antivirus software

(2) Folder Setting

Add 01, 02, 03, 04, and video folder.



Click right mouse button → Properties → Sharing → Add "Everyone" for File Sharing → Select "Read" → Share

Click right mouse button of video folder → Properties → Security → Edit → Select "Everyone" for read-only of Group of user names.

(3) Turn off system function

Internet Time Synchronization

Click the time at lower right side of your computer → Change date and time → Internet time → Change Settings → Uncheck Synchronization with an Internet time server

Disk Defragmenter Schedule

Click Start → Control Panel → Click System and Security → Click Disk defragmenter → Configure schedule → Uncheck Run on a Schedule

Turn Off the Display and Put the Computer to Sleep

Control Panel → System and Security → Power Options → Click Edit Plan Settings → Select "Never" for "turn off the display" and "put the computer to sleep"

System Protection

Control Panel → System and Security → System → System protection → Turn off the protection of the disk

UAC Settings

Control Panel → User Accounts → Change User Account Control Settings → Switch to "Never notify"

Please reboot after settings is finished.

2 Check email for download link download Smartape software installation file



When installing and using the software for the first time, your computer must be connected to the Internet.

3 Install Smartape Software

(1) Open the Smartape installation folder → select Setup.exe file → click right mouse button to check [Run as administrator]

(2) Click and to start installation.

(3) Follow the direction to make sure the install path → Select language → Install success

4 Setting for Run this program an administrator

Select SmartApp.exe file → click the right mouse button → Click Run as administrator .

Program Files

Windows 11 ▶ Search Smartape program at Start → Click right mouse button → Open file